

Disclaimer

Legal disclaimer

This guide and its contents (the "Guide") are provided by NXGEN. All rights to the Guide and to the intellectual property embodied in it — including, without limitation, trademarks, trade names, logos and similar marks appearing in or on it — are protected by law. All right, title and interest in the Guide and in any related intellectual property rights belong to and remain with NXGEN and its licensors.

The Guide is provided free of charge, "as is" and for informational purposes only, without warranty of any kind. It is neither intended nor suitable to establish any legal relationship between the reader and NXGEN or its affiliates, including, without limitation, any obligation of NXGEN or its affiliates toward the reader.

The obligations of NXGEN and its affiliates in respect of NXGEN products or services purchased by a customer are governed exclusively by the terms of the agreement under which those products or services were purchased.

For clarification

The reader bears the entire risk as to the use, results and performance of the Guide. To the fullest extent permitted by applicable law, NXGEN disclaims and excludes all warranties, whether statutory, express or implied — including, without limitation, implied warranties of merchantability, fitness for a particular purpose, title and non-infringement of third-party rights — as well as any liability or warranty arising from suggestions, specifications or samples related to the Guide.

Is GC Surge Working?

Updated 23 September 2026

Summary

This page explains how to measure whether GC Surge is delivering results in your operation. It covers how to measure your baseline alarm processing time, what to expect from each engine, and how to read your Day 7 results. Covers: Establishing Your Baseline APT, What to Expect from Each Engine, APT and Cameras per Operator Are Separate Measurements, Reading Your Day 7 Results, If Results Are Not Yet Visible.

Establishing Your Baseline APT

APT (Alarm Processing Time) is the time from an Operator taking responsibility for a site or alarm to closing its alarms. It is the primary measure of how efficiently your team is working.

Record your APT early so you have a reference point to compare against as the platform delivers results.

NOVA99x is active from the moment cameras are connected, so your very first shift data already reflects filtered alarms.

1. Run at least one full shift in ZenMode. Your operators handle pre-filtered, correlated alarms from the start.
2. At the end of the shift, open Alarm Center — Admin View and note the Avg. Processing Time shown in Top Performers.
3. Record this number. This is your baseline APT — the starting point everything else is measured against.

See [Dashboard KPI Reference](#) for the full definition of APT and how it is calculated.

What to Expect from Each Engine

GC Surge delivers results in stages. Each engine adds to the one before it:

Stage 1 — ZenMode alone (active from Day 1)

ZenMode combines correlated alarms into a single closeable event and processes them in parallel rather than one at a time. In live operation, a workflow of 10 alarms that takes 30 seconds to handle sequentially takes approximately 6 seconds with ZenMode. You will see this reflected in a lower APT from your very first shift.

Stage 2 — NOVA99x active (from Day 1)

NOVA99x removes up to 99% of false alarms before they reach your operators. Combined with ZenMode, the measurable range across live deployments is 85% to 97% less alarm processing time compared to processing alarms without the platform. NOVA99x is always active — no configuration or enabling is required.

Stage 3 — Insights compounds over time

Insights tracks 8 KPIs per operator, per shift, in real time. As your team reviews their performance data shift by shift, handling patterns improve. This compounds the APT gains already delivered by NOVA99x and ZenMode. The result measured across live deployments is 40% more cameras per operator on the same team, and climbing over time.

APT and Cameras per Operator Are Separate Measurements

APT measures how fast an operator handles each alarm. Cameras per Operator (CPO) measures how many cameras the team can cover per shift. Lower APT frees up operator time, which creates the headroom for CPO to grow — but the two figures measure different things. Read them together as two

separate signals that both confirm the platform is working, not as a formula where one directly produces the other.

Reading Your Day 7 Results

At Day 7, GC Surge reads your actual results and displays them on the dashboard alongside a subscription prompt. To review your results yourself before Day 7:

- **APT trend** — open Alarm Center — Admin View — and compare the current Avg. Processing Time against your Day 1 baseline. A drop of 85% or more indicates both engines are working as expected.
- **Cameras per Operator** — shown in the [Dashboard KPI Reference](#) and on the Home dashboard. Compare to your pre-trial staffing ratio.
- **Filter rate** — in Analytics, this shows what percentage of incoming alarms NOVA99x is removing. A healthy filter rate is above 80%.

If Results Are Not Yet Visible

If APT has not improved after several shifts, check the following in order:

1. **Alarm volume.** GC Surge delivers reliable gains when daily alarm volume across the centre is 5,000 or more. Below this threshold the platform works, but the improvement is less consistent. Check your total daily alarms in Analytics.
2. **NOVA99x is active.** NOVA99x is always active from day one — no setup required. If APT improvement seems lower than expected, the full reduction builds as NOVA99x continues filtering and your team runs more shifts.
3. **Cameras are in active alarm-sending state.** If cameras are connected but not generating alarms, ZenMode has nothing to process. Verify alarm forwarding is active on the camera side.

4. Operators are using ZenMode. APT is only recorded when alarms are handled through the ZenMode screen. If operators are closing alarms outside ZenMode, those closures do not contribute to the APT metric.

For setup verification steps, see [Getting Started — Your First 30 Minutes](#). For subscription and trial details, see [Subscription Lifecycle — Trial to Paid](#).